

# Lists Explanation

This page explains the most commonly used Euroscope lists of the EDWW FIR Euroscope Package. All lists (except Sector List) can be activated by clicking on the "Quick SET" option of Euroscope.

Definitions in grey (see tables below) are not displayed by default but can be activated by clicking on the little "F" of each list. The same principle applies when deactivating columns which are displayed by default.

## Sector List

Sector List														
C/S	ATYP	ADEP	ETN	COPN	PEL	ADES	ETX	COPX	XFL	CFL	RFL	DCT	SI	STND
LHA12AK	A320/M	EDDM				EFHK	0843	BODLA	320	320	320	BODLA		
WZZ44	A320/M	EPKK				ENZV	0845	COPX	380	380	380			
LHA8601*	AT76/M	ESMS	0840	SALLO	210	EDDP	0910	SISGO	160	210	210			
AUA562	A320/M	LOWW	0844	COPN	300	EKCH	0907	KOSEB	200	300	300			

The Sector List is used in the Bremen Radar profile. To use this list in the Rhein Radar and Maastricht Radar profile, in the Topsky Menu bar click on "Tools" > "Flight Plan Lists" > "Sector List...".

List Item	Description	Left click	Right click
ASSR	Assigned Squawk Code	Assign Squawk	--
FR	Flight Rule Indicator	--	--
C/S	Callsign	Open Callsign Menu	Toggle Route Draw
C	Communication Type Indicator	Change Communication Type	--
AYTP	Aircraft Type + WTC	--	--
ADEP	Departure Aerodrome	Open Flight Plan	--
ETN	Estimated Time of Sector Entry	--	--
COPN	Sector Entry Waypoint	Open Waypoint Coordination Menu	--
PEL	Planned Sector Entry Level	Open PEL Coordination Menu	--
ADES	Destination Aerodrome	Open Flight Plan	--

ETX	Estimated Time of Sector Exit	--	--
COPX	Sector Exit Waypoint	Open Waypoint Coordination Menu	Open Waypoint Menu
XFL	Sector Exit Level	Open XFL Coordination Menu	--
CFL	Cleared Flight Level	Open CFL Menu	Open RFL Menu
RFL	Requested Final Level	Open RFL Menu	Open RFL Menu
AHDG	Assigned Heading	Open AHDG Menu	Open Waypoint Menu
STAR	Assigned STAR	Open STAR Menu	--
RWY	Assigned Arrival Runway	Open Runway Menu	--
SI	Next Sector Indicator	Open SI Menu	--
STND	Planned Arrival Stand	Open Stand Menu	Open Stand Menu

## Departure List

0 F S

Departure List

REQ	CALLSIGN	STAND	ATYP	W	V	ADES	RWY	SID	VIA	CLMB	aSSR	DCL	C	STS	T	RMK
-	DLH9EM	B06	A320	M		EDDF	25L	LOGD02N	YES	A50	1000					
-	EZY57BT	B10	A320	M		EGGD	25L	SUKIP2N	YES		2023					
-	EJU64GB	C01	A319	M		LTAI	25L	ABSAF2N	YES	A50	2221	OK		SU		
-	MAH801	C05	T154	M		LHBP	25L	LUR0S2N	YES	A50	1000					

Note: When using the Bremen Radar Profile, the ADEP column is also displayed by default.

List Item	Description	Left click	Right click
TIMER	Pending Request Time	--	--
REQ	Pending Request	Open Request Menu	--
CALLSIGN	Callsign	Open Callsign Menu	Toggle Route Draw
TOBT	Target Off-Block Time (CDM)	Set Ready TOBT Status	Open TOBT Menu
TSAT	Target Start-Up Time (CDM)	--	Open CDM Menu
CTOT	Calculated Takeoff Time (CDM)	Open CTOT Menu	Get ECFMP FM as text
STAND	Departure Stand	--	--

ATYP	Aircraft Type	Edit Scratchpad (Remarks)	Open Communication Type Menu
W	WTC highlight	Toggle WTC highlight	--
V	Flight Rules Indicator	--	--
ADEP	Departure Aerodrome	Open Flight Plan	Open Flight Plan
ADES	Destination Aerodromeme	Open Flight Plan	Open Flight Plan
RWY	Assigned Departure Runway	Open Runway Menu	Open Euroscope SID menu
SID	Assigned SID	Confirm proposed runway	Open SID Menu
CLMB	Cleared Level	Open CFL Menu	Open CFL Menu
RFL	Requested Final Level	Open RFL Menu	Open RFL Menu
aSSR	Assigned Squawk	Auto Assign Squawk	Open Squawk Menu
DCL	Datalink Clearance Indicator	Open DCL Menu	--
C	Clearance Received Flag	Set Clearance Received Flag	--
STS	Ground State	Open Ground State Menu	Open Ground State Menu
T	Communication Type Indicator	Open Communication Type Menu	Open Communication Type Menu
RMK	Scratchpad / Remarks	Edit Scratchpad (Remarks)	Edit Scratchpad (Remarks)

## Startup List

REQ	CALLSIGN	C	TOBT	TSAT	CTOT	STAND	ATYP	W	V	ADES	RWY	SID	VIA	CLMB	aSSR	DCL	STS	T	RMK
-	DLH9EM	☐	----			B06	A320	M		EDDF	25L	LOGD02N	YES	A50	1000				
-	EJU64GB	■	----			C01	A319	M		LTAI	25L	BRSAF2N	YES	A50	2221	OK	SU		
-	EZY57BT	☐	----			B10	A320	M		EGGD	25L	SUKIP2N	YES		2023				
-	MAH801	☐	----			C05	T154	M		LHBP	25L	LUROS2N	YES	A50	1000				

By default the Start-Up List is disabled. Especially when working Delivery during events it is recommended to use the Startup list as traffic with taxi, lineup or takeoff ground states are filtered out. To display the Start-Up List click on the "Quick SET" menu in Euroscope, then on "Show Startup List".

List Item	Description	Left click	Right click
<b>TIMER</b>	Pending Request Time	--	--
<b>REQ</b>	Pending Request	Open Request Menu	--
<b>CALLSIGN</b>	Callsign	Open Callsign Menu	Assume/Transfer
<b>C</b>	Clearance Received Flag	Set Clearance Received Flag	--
<b>TOBT</b>	Target Off-Block Time (CDM)	Set Ready TOBT Status	Open TOBT Menu
<b>TSAT</b>	Target Start-Up Time (CDM)	--	Open CDM Menu
<b>CTOT</b>	Calculated Takeoff Time (CDM)	Open CTOT Menu	Get ECFMP FM as text
<b>STAND</b>	Departure Stand	--	Open Stand Menu
<b>ATYP</b>	Aircraft Type	Edit Scratchpad (Remarks)	Open Communication Type Menu
<b>W</b>	WTC highlight	Toggle WTC highlight	--
<b>V</b>	Flight Rules Indicator	--	--
<b>ADES</b>	Destination Aerodromeme	Open Flight Plan	Open Flight Plan
<b>RWY</b>	Assigned Departure Runway	Open Runway Menu	Open Euroscope SID menu
<b>SID</b>	Assigned SID	Confirm proposed runway	Open SID Menu
<b>CLMB</b>	Cleared Level	Open CFL Menu	Open CFL Menu
<b>RFL</b>	Requested Final Level	Open RFL Menu	Open RFL Menu
<b>aSSR</b>	Assigned Squawk	Auto Assign Squawk	Open Squawk Menu
<b>DCL</b>	Datalink Clearance Indicator	Open DCL Menu	Set Clearance Received Flag
<b>STS</b>	Ground State	Open Ground State Menu	Open Ground State Menu
<b>T</b>	Communication Type Indicator	Open Communication Type Menu	Open Communication Type Menu
<b>RMK</b>	Scratchpad / Remarks	Edit Scratchpad (Remarks)	Edit Scratchpad (Remarks)

Revision #8

Created 10 April 2024 15:47:33 by 1395737

Updated 24 December 2024 09:47:31 by 1395737