

Overview

Hamburg Airport is the 5th largest airport in Germany and was opened in 1911, making it **the oldest international airport in the world to still be in operation**. It serves as a hub for Eurowings and Condor, has regular flight schedules from premium European carriers (e.g. Lufthansa, British Airways, KLM) as well as Low Cost carriers and handles a big variety of Aircraft types from small General Aviation planes up to A380s.

EDDH Tier 1 Endorsement is mandatory to control any station in Hamburg or above!

Hamburg ATC Stations

Station	Station ID	Login	Frequency	Remark
ATIS	ADH	EDDH_ATIS	124.325	--
Ground	DHL	EDDH_DEL	121.805	Delivery, Callsign "Ground"
East Apron	DHE	EDDH_E_GND	121.705	--
West Apron	DHW	EDDH_W_GND	121.980	--
Tower	DHT	EDDH_TWR	126.855	--
VFR Tower	DHR	EDDH_VFR_TWR	121.280	Relief Station / Event
Hamburg	HAM	EDDH_APP	120.540	--
Hamburg West	HAMW	EDDH_W_APP	134.255	Relief Station / Event
Arrival	DHAT	EDDH_A_APP	118.205	--

General Information

Hamburg is a restricted Tier 1 airport of the **Bremen FIR**. vACC Germany Controllers can get an endorsement with their S2 rating or higher, visiting Controllers from other countries need a S3 rating or higher. More Info: **Visiting Controller**

All stations on the ground (DEL, GND and TWR) do not have to track aircraft.

Runways

Runway 33 / 15	Runway 23 / 05
Length: 3666m Width: 46m ILS (15), RNP, SRA	Length: 3250m Width: 46m ILS, RNP, SRA ILS 23 (CAT III)

ILS-Frequencies

RWY	Frequency	Identifier	CRS
23	111.3 111.5 (old)	IHHW	228°
15	109.550 111.35 (old)	IHHS	150°
05	110.5	IHHE	047°

Operations Rate

RWY Config	Departures/hour	Arrivals/hour
33/23	31	31
23/15	27	27
33/05	27	27
05/15	20	20
23/23	24	24
33/33	20	20

05/05	22	22
15/15	17	17
33/23 (LVO)	14	14
23/23 (LVO)	12	12

Quicksheet

EDDH Quicksheet

Revision: 20-03-2025

SID

Standard	AMLUH	HABFU	SOKWO	IDEKO	ELSOB	LUGEG	RAMAR	WSN	EDDH
33	2G	1G	1G	7G	3G	3G	6G	5G	1G
23	3B	1B	1B	8B	3B	3B	6B	4B	1B
15	2D	1D	1D	9D	3D	3D	6D	4D	1D
05	2C	1C	1C	8C	3C	3C	6C	5C	1C
DEP FREQ*	120.540	134.255	120.540	134.255	134.255	120.540	120.540	134.255	COORD
INIT CLB	5000 ft								

All SIDs require use of "Climb via SID" phrase, EDDH SIDs are exempt
*DEP FREQ shall be transmitted with clearance during HAM+HAMW split ONLY

STAR

Standard	BOGMU	NOLGO	RARUP	RIBSO
33	3S	3S	3S	3S
23	3P	3P	3P	3P
15	3D	3D/3W**	3D	3D
05	5A/3N***	6A	6A	7A
APP FRQ	120.540	120.540	120.540	134.225
LVL AT	FL 110			

**NOLGO3D east / NOLGO3W west downwind
***BOGMU5A east / BOGMU3N west downwind

Holdings

Fix	BOGMU	HAM	NOLGO	RARUP	RIBSO
MHA	4000 ft				
Max	FL 100 (COORD with ACC required for higher)				
INBD TRK [TURN]	228[R]	005[R]	004[L]	274[R]	026[R]
APP	HAM	HAM	HAM	HAM	HAMW

COMMUNICATION

ID	Freq	Callsign
ADH	124.325	Hamburg ATIS
DHL	121.805	Hamburg Ground
DHE	121.705	Hamburg Apron (East)
DHW	121.980	Hamburg Apron (West)
DHT	126.855	Hamburg Tower
DHR	121.280	Hamburg Tower (VFR)
HAM	120.540	Bremen Radar (Pickup)
HAMW*	134.255	Bremen Radar (Pickup West)
DHAT	118.205	Hamburg Arrival
ALR	126.325	Bremen Radar
HEI	125.855	Bremen Radar
WW	127.675	Bremen Radar
WC	133.725	Bremen Radar

*HAMW is only to be staffed as relief station during rush hour/events

Approach Procedures

RWY	33	23	15	05
APP	RNP	ILS	ILS	ILS
ID	N/A	IHHW	IHHS	IHHE
FREQ	N/A	111.3	109.55	110.5
CRS	329	226	149	046
FAP	SOSAX	PISAS	DEVOD	ANEXI
ALT	3000 ft	3000 ft	3000 ft	3000 ft