

Phoenix Tower Tags - OLD

The Tag has changed with AIRAC 2401 (25. January 2024) for harmonisation within all three FIRs. Detailed documentation will follow by ATD. Most of the items are still the same as discribed below.

Colors

Color	State	Meaning
	Arrival	A/C flying to Aerodrome selected as Arrival in Runway setup
	Departure	A/C flying to Aerodrome selected as Departure in Runway setup
	Urgency	STCA-, MTCD-Alerts, Equipment-Warnings
	Warning	Risk, APW, not confirmed STAR/SID/RWY

Phoenix-Tags

There is no difference between untagged and tagged in the tower profile.

Untagged / Tagged

SQI WARNINGS
CALLSIGN WTC ATYP
AFL↓ GS
DIAS ADES CTL

Item	Name	Meaning
SQI	Squawk Indicator	Decodes SQUAWK into an abbreviation that indicates sth

Warnings		> TopSky-Documentation
Callsign	Callsign	
WTC	Wake-Turbulence Category	L, H and J shown in warning color, M only when toggled
ATYP	Aircraft-Type	only shown when toggled
AFL	Actual Flight Level	
↓	Descend/Climb Indicator	
GS	Groundspeed	
DIAS	Calculated IAS	Simulates MODE-S readout IAS (IASsure-plugin)
CTL	CTL Flag	shown when set

Detailed

SQI WARNINGS
 CALLSIGN WTC ATYP SI
 AFL↓ GS ASP
 DIAS ADES STAND
 SID ARWY CTL

Item	Name	Meaning	Left-Click	Right-Click
SQI	Squawk Indicator	Decodes SQUAWK into an abbreviation that indicates sth	Open CCAMS Squawk assign popup	Open flight plan
Warnings		> TopSky-Documentation		
Callsign	Callsign	in departure/arrival color	Open callsign menu	Toggle route draw (with autohide)
WTC	Wake-Turbulence Category	always shown in departure/arrival color	Open CCAMS Squawk assign popup	Open communication type popup
ATYP	Aircraft-Type		Edit remarktext	Toggle ATYP display

SI	Sector Identifier	Shows current unit that has track assumed	Open next controller popup list	Toggle SI and frequency
AFL	Actual Flight Level		Toggle CTL-Flag	Open CFL menu
↓	Descend/Climb Indicator			
GS	Groundspeed		Open ASP menu	Clear AHDG menu
ASP	Assigned Speed		Open ASP menu	Clear ASP value
DIAS	Calculated IAS	Simulates MODE-S readout IAS (IASsure-plugin)	Open reported IAS menu	Clear reported IAS
ADES	Aerodrome Destination		Open flight plan	Toggle route draw (no autohide)
Stand	Arrival Stand	only shown for arriving aircrafts	Open Stand menu	
ARWY	Arrival Runway	Shown in green confirmed color, if set (only shown for arriving aircrafts)	Open RWY Setup List	Open Stand menu
CTL	CTL Flag	shown when set	Toggle CTL-Flag	
SID		only shown for departing aircrafts	Open SID setup list	

Revision #4

Created 24 March 2023 10:32:20 by 1483787

Updated 13 April 2024 01:38:49 by 1433041