

ATIS Codes

Default ATISmaker URL

“ [https://www.uniatis.net/atis.php?&metar=\\$metar\(\\$atisairport\)&arr=\\$arrwy\(\\$atisairport\)&dep=\\$deprwy\(\\$atisairport\)&apptype=ILS&info=\\$atiscode](https://www.uniatis.net/atis.php?&metar=$metar($atisairport)&arr=$arrwy($atisairport)&dep=$deprwy($atisairport)&apptype=ILS&info=$atiscode) ”

In Berlin, the departure frequency shall not be displayed in the ATIS!

Optional ATIS Codes

Note: Taxi in () are notes only and will not be displayed in the ATIS.

CODE	Broadcast
&lv	[LOW VISIBILITY PROCEDURES IN OPERATION CAT II AND III AVAILABLE]
&indep	[EXPECT][INDEPENDENT PARALLEL ILS APPROACH][RUNWAY] X [AND] Y [] (X,Y runway will be selected automatically)
&gndf=xxx.xxx	[AFTER VACATING RUNWAY] %actrwy_or% [CONTACT GROUND ON FREQUENCY][]xxx.xxx[] (xxx.xxx change with active frequency)
&nognd	[AFTER VACATING RUNWAY] %actrwy_or% [REMAIN ON FREQUENCY][] (%actrwy_or% runway will be selected automatically)
&gnds	[AFTER VACATING RUNWAY][]%actrwy_or%[][CONTACT GROUND ON FREQUENCY][][121.705][](%actrwy_or% runways will be selected automatically)
&gndboth	[AFTER VACATING RUNWAY][]%gndbothrwyone%[][CONTACT GROUND ON FREQUENCY][][129.505[][AFTER VATING RUNWAY][]%gndbothrwytwo%[][CONTACT GROUND ON FREQUENCY][][121.705[] (%gndbothrwyone%,%gndbothrwytwo% runways will be selected automatically)
&drops	[ALL DEPARTURES EXPECT RUNWAY] X (X runway will be selected automatically, to be used during dedicated runway operations)
&windshearall	[WINDSHEAR ALL RUNWAYS]

&windshear24	[WINDSHEAR] [RUNWAY] 24L [AND] 24R
&windshear06	[WINDSHEAR] [RUNWAY] 06L [AND] 06R
&06lwip	[RUNWAY] 06L [CLOSED DUE TO WORK IN PROGRESS][]
&06rwip	[RUNWAY] 06R [CLOSED DUE TO WORK IN PROGRESS][]
&24lwip	[RUNWAY] 24L [CLOSED DUE TO WORK IN PROGRESS][]
&24rwip	[RUNWAY] 24R [CLOSED DUE TO WORK IN PROGRESS][]

Revision #4
Created 12 October 2023 10:21:29 by 1491867
Updated 6 January 2025 13:07:58 by 1395737